

Guide

# M4FX Version 7.1

---

All rights reserved. No part of this documentation may be reproduced in any manner (print, photocopy or other) without the written permission of CAD Schroer GmbH.

CAD Schroer GmbH has made its best effort to ensure that the information in this document is accurate and reliable, but cannot guarantee the accuracy, timeliness, reliability or completeness of any of the information contained herein. CAD Schroer GmbH will not make any warranty nor accept legal responsibility or liability of any kind for consequences resulting from errors or omissions.

Registered Products and Trademarks of CAD Schroer GmbH:  
MEDUSA, STHENO, M4, i4

Products and Trademarks of CAD Schroer GmbH:  
MEDUSA4, STHENO/PRO, MEDEA, MPDS, MPDS4, M4 ISO, M4 P&ID FX, M4 ISO FX

Products and Trademarks of the Parametric Technology Corporation or its subsidiaries in the USA and other countries:  
PTC, PTC Creo, Pro/ENGINEER, Pro/DETAIL, Windchill PDMLink, PTC Mathcad und Pro/TOOLKIT.

All other brand or product names are trademarks or registered trademarks of their respective owners.

November 2021

Copyright © CAD Schroer GmbH

## Germany

**CAD Schroer GmbH**  
**Fritz-Peters-Str. 11**  
**47447 Moers**

Tel. +49 2841 91 84 - 0  
Fax +49 2841 91 84 - 44  
e-mail: [info@cad-schroer.de](mailto:info@cad-schroer.de)  
[www.cad-schroer.de](http://www.cad-schroer.de)

---

# INSTALLATION

---

Please read this guide before you install your M4 ISO FX software - it includes important information on the correct installation of the product.

- [Systems Requirements](#) ..... 4
- [License Types](#) ..... 4
- [Installing M4 ISO FX](#) ..... 5
- [Starting M4 ISO FX](#) ..... 12

## Systems Requirements

### Windows

Operating System	10 Pro 64 Bit
Memory	8 GB and higher
Disk	900 MB free space
Monitor Resolution	1400 x 900 1920 x 1080 recommended
Mouse	3-Button Mouse

## License Types

In order to install M4 ISO FX, you need a license.

Two different types of licenses are available for M4 ISO FX, single-user licenses and network licenses in alternatively a test license.

### Network License

If you purchased a network license, you receive a license file that contains one or more licenses for M4 ISO FX. This requires to install the CSG License Server software on a Windows computer. Please, read the *CSGLicenseServer\_710.pdf* and install the CSG License Server as described.

### Single-User License

This type of license is a host-based license issued for your PC only. It allows you to run M4 ISO FX only on this PC.

The license is usually sent to you by e-mail. Before you start the installation, save the license file to a temporary location on your hard drive (the license file name is for example *FX123456.csghic*).

### Test License

If you have not yet purchased M4 ISO FX and not yet received a license, you can request a free, time limited (30 days) trial license from within the installation program.

## Installing M4 ISO FX

Administration privileges are required to install the software.


During the installation process, you will be prompted for the location of the license file. After the installation is complete, you can delete the license file from the temporary location.

Before you start the installation, please close all applications.

Having started *m4\_iso\_fx\_710\_windows\_x64.exe* the installation files are extracted into the temporary directory. The Installation Wizard will then be launched.

### Installation Wizard


In the first window of the Installation Wizard choose the language for the Installation Wizard. The actual M4 ISO FX product language can be chosen in a later step.




# M4 ISO FX 7.1 Installation




Click **Next** on the welcome screen.



Choose the M4 ISO FX installation folder. Please ensure that the path name contains no blank spaces or special characters, which is why the default installation path cannot be *C:\Program Files*.



Choose the M4 ISO FX software language and click Next.



# M4 ISO FX 7.1 Installation



Select the license.

If you purchased a network license, specify the host name of your server.

If you purchased a single-user license, enter the path of the license file you received from CAD Schroer or select the file.

Alternatively, you can request a free trial license, an Internet connection is required.

Click Next.

M4 ISO FX V7.1.0

**M4 ISO FX V7.1.0**

License

Choose your license file :

License server

Please enter the host name of your license server.

License file

Please enter the license file provided by CAD Schroer.  
Please note that this license is only valid for one computer.

M4 ISO FX trial


Request a free trial license and test our software for 30 days.  
An Internet connection is required.

CAD Schroer Group

< Back    Next >    Cancel

M4 ISO FX provides its documentation in PDF format. The documentation can be viewed either in a web browser (Microsoft Edge, Mozilla Firefox or Google Chrome) or directly in Adobe Reader. Adobe Reader DC is supported.


Select the path of your web browser.




# M4 ISO FX 7.1 Installation




For viewing the help you can choose between two options as described before.




Click on **Next**. The screen displays the installation location and the required and available space on your computer.




Click on Next to start the installation process.



The Master Project is created.



The Wizard reports the successful installation. Click **Finish** to close the Installation Wizard.



## Starting M4 ISO FX

During the installation a folder is created in the Start menu and a link on your desktop.

The easiest way to start M4 ISO FX is a double click on the icon .